## **Level Detector**

**V**Carrara

## **Definition**

The Level Detector is a small code placed before any effect that aims to compute the input audio level. The level can then be used by any effect with LFFG (Low Frequency and Function Generator) configured with LFO\_LEVEL or LFO\_REVERSE\_LEVEL to modulate a specific parameter, like the Wah Wah or Tremolo, for instance. The effects that can be affected by Level Detector are

- Chorus (*chr*)
- Phaser (*phr*)
- Tremolo (tml)
- Vibrato (*vbt*)
- Volume (vol)
- Wahwah (wah)

## **Level Detector**

The adopted algorithm for the Level Detector is exactly the same of the Compressor<sup>1,2</sup> effect, except that it does not compress the input audio. The model for the Level Detector was extracted from Compressor documentation and is reproduced here.

Given the input at sampled time n,  $x_L[n]$ , the best approach to compute the input level  $y_L[n]$  is achieved with the decoupled smooth peak detector<sup>3</sup> which responds quickly when the input level rises, but decreases slowly when the input level fades:

$$y_1[n] = \max (x_L[n], \alpha_R y_1[n-1] + (1-\alpha_R) x_L[n])$$

So the smoothed output level becomes

$$y_L[n] = \alpha_A y_L[n-1] + (1-\alpha_A) y_1[n]$$

where  $\alpha_A$  and  $\alpha_R$  are the low-pass filter attack and release parameters, respectively, obtained from

$$\alpha_A = e^{-\frac{1}{\tau_A f_s}}$$

and

$$\alpha_{R} = e^{-\frac{1}{\tau_{R} f_{s}}}$$

in which  $\tau_A$  is the attack time and  $\tau_R$  is the release time.

## References

- Wikipedia. Dynamic Range Compression. Available at: <a href="https://en.wikipedia.org/wiki/Dynamic range compression">https://en.wikipedia.org/wiki/Dynamic range compression</a>>, 2023.
- McNally, G. W. Dinamic Range Control of Digital Audio Signals. Journal of the Audio Engineering Society, Vol. 32, No. 5, May 1984.
- Giannoulis, D.; Massberg, M.; Reiss, J. Digital Dynamic Range Compressor Design A Tutorial and Analysis. Journal Audio Engineering Society, Vol. 60, No. 6, June 2012.